The instruction of DSP3+ software update

Please install ActiveSync software on your PC well before software update. Or please log in <u>http://smelecom.com/sm/download.htm</u> and download ActiveSync software and install it on your PC first of all.

Home	News	Products	Download Sales	Online-Shopping	
Data Specialist F	Plus 3+	• USA PROG	• M-CORRECTOR	Airbag	
Data Smart 3+		VAG PROG	CAN-BLOCKER	• Immo	
Software					
Datasmart III, VAG PROG and USA PROG (version:2.0.0.9.5 run on windows XP, win7)			PC_link setup.exe		
DataSpecialist III ActiveSync (windows XP)			ActiveSync(setup.msi)		
DataSpecialist III ActiveSync (windows 7)		ActiveSync(32bit win	7) ActiveSync(64bit win7)		
Data Smoot III Llaada driver			driver32.rar (32bit windows XP,win7)		
Data Smart III Oser S unver		driver64.rar (64bit win7)			
A4_Decoder Setup(2009.2.3)			A4_Decoder Setup		
TMS programmer Software			tms.rar	tms.rar	
9S12 In_circuit Programmer Setup			9S12 In_circuit Programmer Setup.exe		
NEC programmer Software			NECPROG.exe		
Driver(for old USA prog and VAG dash prog)			User's driver.rar		

The steps are similar among "Function Sync" and "Active Function" and "Software Update", take "Software update" as an example:



1. Connect test connector and power supply well, shown as figure 1:

Figure 1

2. Click the red circle, and input the password, click button "ok", shown as figure 2:

	6.0
请输入密码然后点击OK	1 2 3 4
	5 6 7 8
	9 0 A B
	C D E F
修改密码	DEL OK Cancel

3、Connect USB cable to the dsp3+, shown as figure 3:



Figure 3

4. If your PC is windows XP operation system, set your ActiveSync software as figure 4.1:



Figure 4.1

If your PC is windows7 operation system, set your pc as figure 4.2:



Figure 4.2

5、 XP operation system set successfully, shown as figure 5.1:



Figure 5.1

Windows7 operation system set successfully, shown as figure 5.2:



Figure 5.2

6、 Click "Update" on the screen of DSP3+, and then click "SOFTWARE UPDATE', shown as figure 6:





Click "YES" to start software update.

Note: this process will take about 30 minutes, during this time, do not disconnect the power supply, do not disconnect USB cable, do not change any settings on PC, wait patiently please.

7、 About 30 minutes later, you will see "update successfully" on the screen of DSP3+, shown as figure 7:



Figure 7

Software update successfully.